

Listeners Configuration

Description

This section describes the management environment of Listener, which enables detection of various events in Pre and Post of Job, Step, and Chunk during the process of Batch Jobs.


| Item | Sub-category | Description |
|-----------|--------------|---|
| Listeners | Job | Detects events before and after each Job performed. |
| | Step | Detects events before and after each Step performed. |
| | Chunk | Detects events before and after each Chunk performed. |

How to Use


Configuring Job Listener

Components of Job Listener

1. In the menu bar, choose **Window>Preferences**.




2. From the list on the right side of the Preferences Page, select **eGovFrame>Batch>Listener**, then select the **Job Tab** then click the "New" button.




3. Input desired name of the Job Listener to be registered and add respective Listener Class. Then, select "confirm" to add a new Job Listener.

Keep in mind that the name of the new Job Listener must be different from previously added Job Listener.




Application of Job Listener during creation of Batch Job File


1. In order to create a new Batch Job File through [Batch Job Wizard](#), click on the **Add** button located on the bottom of "Job Listener" from "Job Add"



2. From the list of Job Listeners, select the Listener to be registered and click OK.




3. Confirm Listener Registration in Job Listeners of Batch Job Wizard




Configuring Step Listener

Components of Step Listener

1. In the menu bar, choose **Window>Preferences**.




2. From the list on the right side of the Preferences Page, select **eGovFrame>Batch>Listener**, then select the **Step Tab** then click the "New" button.




3. Input desired name of the Step Listener to be registered and add respective Listener Class. Then, select "confirm" to add a new Step Listener.

Keep in mind that the name of the new Step Listener must be different from previously added Step Listener.




Application of Step Listener during creation of Batch Job File


1. In order to create a new Batch Job File through [Batch Job Wizard](#), click on the **Add** button located on the right side of "Step Listener" from "Step Add"



2. From the list of Step Listeners, select the Listener to be registered and click OK.




3. Confirm Listener Registration in Step Listeners > Listener of the Batch Job Wizard




Configuring Chunk Listener

Components of Chunk Listener


1. In the menu bar, choose **Window>Preferences**.



2. From the list on the right side of the Preferences Page, select **eGovFrame>Batch>Listener**, then select the **Chunk Listener Tab** then click the "New" button.




3. Input desired name of the Chunk Listener to be registered and add respective Listener Class. Then, select "confirm" to add a new Chunk Listener.
 ✓ Keep in mind that the name of the new Chunk Listener must be different from previously added Chunk Listener.




Application of Chunk Listener during creation of Batch Job File

1. In order to create a new Batch Job File through [Batch Job Wizard](#), click on the **Add** button located on the right side of "Chunk Listener" from "Step Add"



2. From the list of Chunk Listeners, select the Listener to be registered and click OK.



3. Confirm that the Listener has been registered in Chunk Listeners of Batch Job Wizard.

